
## Requirements:

- 1. windows pc, win10 is beter.
- 2. usb type-c cable with data transfer, change one if does not work.
- 3. software: flash download tool.exe
- 4. firmware: BURN\_CUBIC\_V3.1.7.bin


## Step 1:

Unzip the rar file, find flash\_download\_tool.exe, double click, choose the ChipType ESP32, and click OK, like below:



## Step 2:


Click the three dot "...", choose the right file, located in "bin" dir.




COM port depend on your USB device, choose your own, it's not COM1. If no other COM port is appreared, please change a usb cable.

Maybe usb driver is needed to be installed! CH340 driver is needed. BAUD set to 921600 is enough.

When all is ready, Click start, and wait it done. flashing image:



## flash done:



Then repower your gadget, good luck!!!

Contact me if you have uncertain questions.

Thank you!!!